

EMP

Cancellation at exit XML

Implementation manual

Version 1.4.0/E

(Valid from November 2024)

DAKOSY
Datenkommunikationssystem AG

Mattentwiete 2
20457 Hamburg
www.dakosy.de

Phone: + 49 40 37003 0
info@dakosy.de

Change history

Version	Type of change	Changed by/ date	Checked by/ date
1.1.0/E	First valid version	24.08.2023	24.08.2023
1.4.0/E	Increase of the version number in connection with the creation of scheme guides for Port Order Types.	24.10.2024	24.20.2024

Change requests

DAKOSY

Datenkommunikationssystem AG

Mattentwiete 2

20457 Hamburg

1. Phone: + 49 40 37003 0

2. Email: info@dakosy.de

Used tools

Number	Used tools
W1	This document was created with MS Word 2021 .

Liability

1. Despite careful development and verification of this document no liability can be derived from the content of this manual towards DAKOSY AG!

Table of contents

1	Introduction	4
2	Strukturaufbau.....	5
3	Guideline	6

1 Introduction

In the customs process of a Port Order with the AES customs procedure, it may occur that the 2nd stage of the AES procedure in the ATLAS system shall be cancelled after the Port Order already has been cancelled. In such cases, the declaration for the 2nd stage of the ATLAS AES procedure is withdrawn.

For this process, the message „Cancellation at Exit“ XML serves as a message that triggers the cancellation of the MRN in ATLAS in the Export Management Platform (EMP(ZAPP)).




Image 1 Integration of the Cancellation at exit XML message in the port communication system.

In this case, only the MRN to be cancelled and the EORI details of the participant are transmitted to the Export Management Platform. This platform then takes over the further communication with the ATLAS system.

2 Strukturaufbau

Occurrence	Element/Attribute
	CancellationAtExit
1 .. 1	xs:sequence
1 .. 1	Transaction
1 .. 1	xs:sequence
1 .. 1	IOPartner
1 .. 1	IOReference
1 .. 1	IODateTime
1 .. 1	MessageVersion
0 .. 1	TestIndicator
1 .. 1	Message
1 .. 1	xs:sequence
1 .. 1	MRN
1 .. 1	Forwarder
1 .. 1	xs:sequence
1 .. 1	DakosyCode
1 .. 1	Identification
1 .. 1	xs:sequence
1 .. 1	EORINumber
1 .. 1	BranchNumber

3 Guideline

Element/Attribute	Annotation
CancellationAtExit	Type CancellationAtExitElementType
xs:sequence	Occurrence 1 .. 1
Transaction	Occurrence 1 .. 1 Type CancellationAtExitTransactionType
xs:sequence	Occurrence 1 .. 1
IOPartner	Occurrence 1 .. 1 Type an..4 Length .. 4 Description DAKOSY participant code
IOReference	Occurrence 1 .. 1 Type an..14 Length .. 14 Description Unique and unambiguous transaction identification reference
IODateTime	Occurrence 1 .. 1 Type xs:dateTime Description Date and time of message creation - ISO 8601 Coordinated Universal Time (UTC) or local time with offset to UTC.
MessageVersion	Occurrence 1 .. 1 Type an..12 Length .. 12 Description Used message version
TestIndicator	Occurrence 0 .. 1 Type xs:boolean Description Test indicator - Indicates whether or not the message is a test message. If the element is not specified or specified as "true", it is about a production message.
Message	Occurrence 1 .. 1 Type CancellationAtExitMessageType
xs:sequence	Occurrence 1 .. 1
MRN	Occurrence 1 .. 1 Type mrnType Pattern \d{2}[A-Z]{2}[a-zA-Z\d]{14} Description Master Reference Number (previously Movement Reference Number) to be cancelled at exit
Forwarder	Occurrence 1 .. 1 Type ForwarderType
xs:sequence	Occurrence 1 .. 1
DakosyCode	Occurrence 1 .. 1 Type an..4 Length .. 4 Description DAKOSY participant code
Identification	Occurrence 1 .. 1 Type IdentificationType
xs:sequence	Occurrence 1 .. 1
EORINumber	Occurrence 1 .. 1 Type eoriNumberType Length 4 .. 17 Pattern [A-Z]{2}[0-9A-Z]{2,15} Description EORI number
BranchNumber	Occurrence 1 .. 1 Type n4 FractionDigits 0 TotalDigits 4 Pattern \d{4} Description Branch number, set to 0000 if not registered.